PETERPANPATTERN

Detachable Peter Pan Collar:

So simple yet beautiful, isn't it? With this cute and easy to crochet detachable Peter Pan collar you pimp up any garment in a jiffy!

Have fun making it and wear it with love.

© Jasz Schneider

A free Crochet Pattern for a detatchable Peter Pan Collar

Brought to you by Jasz Schneider

Requirements

Supplies
Yarn: e.g. 100% cotton, size 3, in your fave colors, I used grey (C1) and cream (C2).
(Silk) ribbon in C2.
Crochet hook, size 3mm (as recommended on yarn). If you're a loose crocheteer better use a hook size smaller.
Stitch marker (I use paper clips).
Yarn needle.

Stitches (**american terminology**)
You should be familiar with chains (casting on), single crochet, half double crochet, increasing and decreasing and crab (reverse) stitch.

Abbreviations
sc – single crochet, m – make, ch - chain, hdc – half double crochet

Generally
At the end of each row (except last) *always* make a turn chain (+1), even if not mentioned.

Rights
You may use this pattern for yourself and gift making only. Please do not sell your results or sell or copy this pattern. Instead feel free to share it using the original source from my ravelry store.
http://www.ravelry.com/designers/jasz-schneider Thank you and enjoy!

A free Crochet Pattern for
a detatchable Peter Pan Collar

**Brought to you by Jasz Schneider**

Pattern

| Row	Stitches	Description
1	81 + 1	chain 81, ch 1, turn
2	81+2	skip 1, sc in each to the end, ch 2, turn
3		**One and only special row** *that's where you lace the ribbon through later* hdc across to the end, ch 1, turn
		mark 41st st. that's our mirror point labelled in the following pattern with a vertical bar "|". It obviously indicates the point where you mirror all stitches :) Set marker a row higher as you go.
4	89 +1	make 2 sc in 3rd, 6th, 9th, 12th	69th, 72th, 75th, 78th st, turn
5	98 +1	make 2 sc in each 10th (to 80th), turn
6	108 +1	make 2 sc in each 7th to 42th st	starting with 56st st, m 2 in each 7th to 91st st, sc to end turn *or* counting: 7th, 14th, 21th, 28th, 35th, 42nd	56st, 63th, 70th, 77th, 84th, 91th.
7	120 +1	make 2 sc in 12th, 24th	96th, 108th st, turn
8		work even, turn
9	134 +1	make 2 sc in each 8th st to 56th	starting with 64th st, m 2 in each 8th to 112th st, sc to end, turn *or* counting: 8th, 16th, 24th, 32nd, 40th, 48th, 56th	64th, 72nd, 80th, 88th, 96th, 104th, 112th.
10		work even, turn
11	132 +1	dec 2nd and 2nd to last (133th) st, turn
12		work even, turn
13	130 +1	dec 3rd and 3rd to last (129th) st, turn
14	128 +1	dec 2rd and 2nd to last (128th) st, end, hide yarn.
		Decide which one's your sunny side.

A free Crochet Pattern for a detatchable Peter Pan Collar

Brought to you by Jasz Schneider

Finish

With the sunny side up, join C1 (grey) into 1st st, crab stitch (reverse stitch) to the end, end, hide yarn.

With the sunny side up, join C2 (cream) in 1st of 3rd row, crab stitch all around the curved side of you collar to the 3rd to last stitch on the other side, end, hide yarn.

Weave in all loose ends. Lace in your ribbon through the half-double-crochet row using a yarn needle.

And you are done! :)

A free Crochet Pattern for
a detatchable Peter Pan Collar

Brought to you by Jasz Schneider

***

If you have any question or suggestion please don't hesitate to email me at
she at jaszmade dot com. Your support is very appreciated. Thanks a lot!

The Author

Jasz Schneider

Websites:

jaszmade.com

jasztheschneider.
wordpress.com

blender70.com

About the Author

Jasmin "Jasz" Schneider, a lifestyle illustrator, skinny food blogger, dolly designer and restorer, devoted seamstress and passionate crafter can't help spilling over with creative ideas to share.

Like her artwork her crochet patterns combine vintage influences with a distinct modern touch, they are unique, easy to follow and 100% made with love.